

# Diagnostic tests and how to test them


Argha Chatterjee
Associate consultant, Radiology and Imaging
Tata Medical Center, Kolkata

Email: arghachat84@gmail.com

# **Gold standard:**

- Must be more elaborate/ risky/ time consuming/ expensive.
- Must have least error/ bias
- Must be different from the test in question!

- How many diseased and non-diseased can be correctly identified?
  - If I perform this test on 100 diseased persons how many will be positive?
  - If I perform this test on 100 normal persons how many will be negative?
- The diagnosis of "diseased" vs "not diseased" is obviously made by the Gold/ reference standard.



	Disease	9	Diseas		Total
	present	t /	е		
	(D+)	/	absent (D-)	$  \setminus $	
Test positive (T+)	90		20		110
Test negative (T-)	10		80		90
Total	100		100		200

How many diseased and non-diseased can be correctly identified?

- Sensitivity tells you if you perform this test on 100 diseased people how many will be positive?
- Sensitivity = True positive/ Total diseased.
- Specificity tell you if you perform this test on 100 normal people how many will be negative?
- Specificity = True negative/ Total non-diseased.

- Sensitivity and specificity are indicators how good a test is compared to a gold standard.
- Sensitivity and specificity describe test performance in people with known disease status.
- These are not dependent on disease prevalence.
- It tells you nothing about how likely disease is present in a particular patient.

# How sure are you that disease is present?

				i
	Disease	Diseas	Total	
	present	е		
	(D+)	absent		
		(D-)		
Test positive	90	20	110	
(T+)				
Test (negative	10	80	90	
(T-)				
Total	100	100	200	

- Positive predictive value tells you if 100 people are positive how many will have the disease?
- PPV = True positive/Total positive
- Negative predictive value tells you if 100 people are negative how many will not have the disease?
- NPV = True negative/ total negative

# How sure are you that disease is present?

- PPV and NPV are indicators how well the test performs in real world.
- PPV and NPV describe test performance in people with unknown disease status.
- These are dependent on disease prevalence.

	Disease present (D+)	Disease absent (D-)	Total
Test positive (T+)	True positive	False positive	Total positive
Test negative (T-)	False negative	True negativ e	Total Negative
Total	Total disease	Total normal	Total population

"Snout" = sensitive - negative - out.

"Spin" = specific - positive - in

Sensitivity ignores false positives.

Specificity ignores false negatives.


However, in real life, if true positives are very high in number, false negative number approaches zero. So a very sensitive test tend to have very low false negative and consequently very high

NPV.

# How to calculate predictive value from prevalence?

- PPV = (Sensitivity x prevalence)/ [Sensitivity x prevalence + (1-specificity)x (1-prevalence)]
- NPV = [Specificity x (100-prevalence)]/[(100-sensitivity) x prevalence +
   Specificity x (100-prevalence)]

# Dichotomy and cut-off



- Calculation of sensitivity, specificity and predictive value requires dichotomising of data [yes/no or disease present/absent].
- For test with continuous/ interval measurements ROC curve helps in selecting cut-off.

# **Summary**

- How many will be positive if 100 diseased people are tested?
   Sensitivity
- How many will be negative if 100 non-diseased people are tested?
   Specificity
  - How many among 100 test positives will have the disease?
     PPV
  - How many among 100 test negative do not have the disease?
     NPV

# Likelihood Ratio

# **Probability versus Odds**

- Probability:
  - Rate of occurrence of an event

- Odds:
  - Probability of an event happening divided by the probability of the event not happening.

If a horse wins 80 out of 100 races, the probability of it winning the next race is 80% but the Odds of it winning the next race is (probability of winning ~ 80%)/(probability of not winning ~20%), i.e. 4 to 1. So if you bet against the horse you will get 4 rupees for every 1 rupees.

Probability = 80% and Odds = 4 or 4:1

### **Probability versus Odds**




Odds

Number of occurence of event under question

Probability of the event of occuring

Total number of events

Probability of the event not occuring



Probability

1 - probability

## **Probability versus Odds**

Pre test Odds =

Pre test probability

1 - pre test probability

#### Likelihood ratio

	Disease present (D+)	Disease absent (D-)	Total
Test positive (T+)	Α	В	Total positive
Test negative (T-)	С	D	Total Negative
Total	Total disease	Total normal	Total population

#### Positive likelihood ratio [LR+]:

- Probability of a test being positive in a diseased person vs Probability of a test being positive in a non-diseased person.
- (LR+) = [Probability of positive test in diseased] ÷ [Probability of positive test in non-diseased]

$$= [A/(A+C)] \div [B/(B+D)]$$

= Sensitivity/(1 - specificity).

[D/(B+D)] = Specificity, hence, B/(B+D) = 1 - specificity

#### Likelihood ratio

	Disease present (D+)	Disease absent (D-)	Total
Test positive (T+)	Α	В	Total positive
Test negative (T-)	С	D	Total Negative
Total	Total disease	Total normal	Total population

#### Negative likelihood ratio [LR+]:

- Probability of a test being negative in a diseased person vs probability of a test being negative in a non-diseased person.
- (LR+) = [Probability of negative test in diseased] ÷ [Probability of negative test in non-diseased]

$$= [C/(A+C)] \div [D/(B+D)]$$

= (1- sensitivity)/Specificity.

## Meaning of likelihood ratio

- (LR+) = 5 means if we run a test a positive result is 5 times more likely in presence of disease than in the absence of disease.
- (LR-) = 0.5 means if we run a test a negative result is twice more likely in absence of the disease than in the presence of disease.

Pre-test Odds x Likelihood ratio = Post-test Odds

## Calculation of pre-test and post-test probability

- Pre test probability means probability of having the disease even before any test is done. This usually means prevalence.
- Post test probability means probability of having the disease after the test is done.
- Positive predictive value = post-test probability.


## Calculation of post-test probability from LR:

- Prevalence of disease = pre-test probability [p]
- Pre-test Odds [d] = p/(1-p)
- Pre test Odds x (LR+) = Post-test Odds [d']
- Post test probability (p') = d'/(1+d')

### **Advantages of likelihood ratio**

- Can be applied at different levels of the same test. Does not require the dichotomous cut-off of sensitivity and specificity.
- Can be applied to serial tests to calculate the post-test probability after an entire battery of tests.

### **Advantages of likelihood ratio**



# Diagnostic tests

## Inaccurate assessment of sensitivity and specificity

- Incorrect gold standard.
- Spectrum of patients:
  - Sensitivity is high in presence of severe disease.
  - Specificity is high in screening population.
- Bias.
  - Gold standard and index test should be different, independent of each other and blinded to each other.
- Statistical uncertainty/ chance
  - Always look at 95% confidence interval while reading a study.

### **Determinants of predictive value**

- Sensitivity
- Specificity
- Prevalence

Always determine prevalence before performing the test to know the post-test probability.

- How to increase pre-test probability?
- Specifics of clinical situation [History, examination, risk factors].
- Demographics [GB cancer more likely in North India].
- Referral process [rare diseases more common in teaching hospital].

# Take home points

- Sensitivity and specificity tells you how good a test is.
- PPV and NPV tells how likely disease is present.
- Likelihood ratio helps you calculate probability of disease at multiple levels of same tests and after serial tests.
- While reading a paper check for chance and biases.
- Before ordering a test increase the pre-test probability.
- Never forget what is the prevalence of the disease in question never expect a zebra when you hear hooves.